Alberta Health Services

Collection?

South Zone Urine Collection -Cytology

How to prepare	 Wash hands thoroughly with soap and water. Remove lid from empty sterile container. DO NOT touch the inside of the container or the lid. Open the antiseptic towelettes and removed from package. 	
	• Open the antiseptic towelettes and removed in	Jili package.
Risks or Cautions	 The fluid in the specimen container is POISON (CytoLyt Solution – Contains: Buffered Methanol). If swallowed, call POISON CONTROL (1-800-332-1414). DO NOT discard fluid. Collect specimens Sunday through Thursday NOT Friday or Saturday (this is to avoid urine sitting for a prolonged period). DO NOT use first morning voided urine. If doctor orders more than one urine specimen, each specimen must be collect on a separate day 	
Labelling the Sample	Immigration, Passport #)	identification such as (Federal, Military, RCMP, attach this label to the outside of the container.
Lab Requisition	 Print the date/time the sample was collected on your lab requisition. Fold and place the requisition in the <u>outside</u> pocket of the biohazard bag. Do not put the requisition in the bag with the sample collection container. 	
Collecting the Sample	Please see reverse for instructions	
Comple		
Sample Delivery to Lab	Return sample and requisition to the laboratory	
	If You are able to deliver the sample within 30 minutes of collection	Then Store sample at room temperature
	You are unable to deliver the sample within 30 minutes of collection	Refrigerate sample for up to 24 hours
	 Prolonged delays may affect the test results. 	
Questions About Your	Lethbridge – (403) 388-6057 Medicine Hat – (403) 529-8919	



South Zone Urine Collection -Cytology

Male

Collecting the Sample -	1. Retract the foreskin (if not circumcised) and wipe penis with towelette provided wiping from urethral opening toward you. Repeat with second towelette. Discard towelettes into garbage can, not into toilet.	
	2. With foreskin retracted urinate (pee) a small amount of urine into the toilet then, without stopping, urinate into the container. Do not over fill the container. Excess urine maybe passed into the toilet.	
	3. Place lid on container and mix urine by gently inverting container several times.	
	4. Transfer a portion of your urine into the container with the fluid supplied by the laboratory. Add urin until the total liquid volume reaches the fill line indicated on the container.	
	5. Firmly tighten the lid onto the container. Dry the outside of the container if it is wet.	
	6. Wash hands thoroughly with soap and water after collection.	
	7. Place container into biohazard bag.	

Female

Collecting the Sample	1. Sit on the toilet and hold labia (lips) apart. Thoroughly clean genital area with		
	towelette provided using a front to back motion. Repeat with second towelette. Allow to air dry completely before urinating (peeing). Do not wipe dry. Discard towelettes into garbage can, not into toilet.		
	2. Continue to hold labia apart while urinating. Urinate (pee) a small amount of urine into the toilet then, without stopping, urinate into the container. Do not over fill the container. Excess urine maybe passed into the toilet.		
	3. Place lid tightly on container and gently mix urine by inverting container several times.		
	4. Transfer a portion of your urine into the container with the fluid supplied by the laboratory. Add urine until the total liquid volume reaches the fill line indicated on the container.		
	5. Firmly tighten the lid onto the container. Dry the outside of the container if it is wet.		
	6. Wash hands thoroughly with soap and water after collection.		
	7. Place container into biohazard bag.		